

Simulated Railroad Framework, <http://simulrr.sourceforge.net>  
Synopsis: [000\\_Synopsis](#)

This file valid for step 0033.10  
Issue Date: 2017-03-17

Modules  
=====

## 1 Synopsis -----

Each Simple Multiuser Scene contains exactly one frame. The frame is the set of all common functions that support the modules and the models when providing virtual senses and skills to the user.

The concepts of SMS require that modules and models are built by declarative 3D principles. However this does not hold for the frame. The frame may be any kind of software that integrates the top level modules into a VR/AR platform.

Within the present Concepts' Descriptions there is not a specific paper for the frame, reason is the above mentioned fact that frames may be very different and it's hard to specify any requirements for the frame.

However, one of the responsibilities of the frame is to load, initialize and optionally disable and unload the top level modules.

Simple Multiuser Scenes are built by modules (an SMS comprises a frame and at least one module), each module can be provided by a different author.

Modules are enriched by models, where the X3D standard and the present concepts guarantee interoperability and re-usability of models, modules and frames.

## 2 Purpose -----

Why is an SrrTrains layout / a Simple Multiuser Scene built by modules?  
Well, there are several reasons.

- 1) a *\*real\** model railroad can be built by modules, too.
- 2) combining modules into an SMS enables more than one author to contribute to one SMS.
- 3) slicing an SMS into modules can save memory and/or CPU resources,
  - a) because a module can be deactivated (switch off animation/simulation)
  - b) because a module can be unloaded completely (i.e. it disappears)

### 2.1 Static Modules -----

If a module is referenced, loaded and initialized immediately after the initialization of the Simple Scene Controller, and if the module is never unloaded at runtime of the scene instance, then we call this module a "static" module.

Static modules can be deactivated or activated at any time. Activation/deactivation is a local category, i.e. it happens only within the scope of one scene instance. A module can be active in one scene instance and inactive in another scene instance.

The SRR/SMUOS Framework uses single character indications for the activity of static modules:

- 'o' the module has not yet been initialized
- '-' the module is inactive (in this scene instance)
- '+' the module is active (in this scene instance)
- '\*' the module is active and it has got the MOC role

Only one instance of the module can have the MOC role.

## 2.2 Dynamic Modules

---

If a module is loaded or unloaded on demand, during the lifetime of the scene instance, then we call this module a "dynamic" module. It is the task of the frame to load/unload dynamic modules and to trigger their initialization upon loading and their disabling before unloading.

Loading/unloading is a local category, i.e. it happens only within the scope of one scene instance. An exception to this rule is the global deregistration of a module, when the Simple Scene Controller triggers the unloading of the module in all scene instances.

Dynamic modules can be deactivated or activated at any time, given they have been loaded and initialized. Activation/deactivation is a local category, i.e. it happens only within the scope of one scene instance. A module can be active in one scene instance and inactive in another scene instance.

The SRR/SMUOS Framework uses single character indications for the activity of dynamic modules:

- 'o' the module has not yet been loaded/initialized, or it has been unloaded
- '-' the module is inactive, but has been loaded (in this scene instance)
- '+' the module is active (in this scene instance)
- '\*' the module is active and it has got the MOC role

Only one instance of the module can have the MOC role.

## 2.3 Dependent Modules (aka Moving Modules)

---

\*Not yet implemented\*

## 2.4 Registration and Deregistration of Modules

---

Registration is the process of

- assigning a moduleIx (SFInt32) to a moduleName (SFString)
- reserving space in the "Communication State" (commState) for the data of the module

The moduleIx of a module is a global category. It has the same value for a given module in all scene instances.

\*Implicit Registration\* is done by the SRR/SMUOS Framework automatically, during the announcement of the module at the Simple Scene Controller. Registration is only done, if the module has not been registered yet.

\*Explicit Registration\* is a feature, that can be used by the frame to learn the moduleIx of a module prior to loading and initializing it.

Explicit registration is useful for dynamic modules, because in many cases the frame will need to store data of the dynamic module in some arrays, before the module is actually loaded and initialized. With this feature, the frame can use the moduleIx as an index into these arrays.

Modules that have been implicitly registered, are automatically deregistered, when the last instance of the module has been unloaded.

Modules that have been explicitly registered, will stay registered, until the frame deregisters them explicitly.

### 3 External View

---

The following interface definition is called "miModule" (minimum interface that a module must provide to be an SMS module)

In case of statically loading a module,

- the frame needs to know the URL of the file, where the module is stored
- the frame needs an indication, which module wrapper shall be used
- the frame needs the field "moduleName" of the module wrapper to set the module name (the frame is responsible for keeping all module names unique)
- the frame needs the field "commParam" of the module wrapper to trigger the initialization of the module (by <ROUTE>ing commParam from the Simple Scene Controller to the module wrapper)

In case of dynamically loading a module,

- the frame needs to know the URL of the file, where the module is stored
- the frame needs an indication, which module wrapper shall be used
- the frame needs the field "moduleName" of the module wrapper to set the module name (the frame is responsible for keeping all module names unique)
- the frame needs the field "commParam" of the module wrapper to trigger the initialization of the module
- the frame needs the field "initialized" of the module wrapper to test whether the module was successfully loaded and initialized (returns a value not equal NULL in case of success and a value of NULL in case of failure)
- the frame needs the field "disable" of the module wrapper to disable the module before unloading it

In both cases,

- the module wrapper needs
  - the field "moduleName" of the module to forward the module name from the frame to the module
  - the field "mwParam" of the module to forward a reference of the module wrapper parameters to the module coordinator
  - the field "commParam" of the module to forward the common parameters from the frame to the module
  - to be sure, that the <ProtoInstance> is the only(!) node in the file of the module (after the <ProtoDeclare> - which does not count)
  - the field "initialized" (SFNode) to test, whether the initialization was successful (returns a value not equal NULL in case of success and a value of NULL in case of failure)
  - the field "disable" to detach and disable the module before unloading it

## 4 Internal View

Typically, a module is implemented in a separate file, that contains the <Scene>

- with a <ProtoDeclare> with the definition of the module
- with a <ProtoInstance> of the module

The <ProtoDeclare> contains the definition of the module, typically comprising

- the module coordinator (a <ProtoInstance>)
- some landscape
- some viewpoints and their avatar container(s)
- references to static models
- intrinsic models (incl. References to MIDAS Objects)
- <ROUTE>s to route the "modParam" event from the module coordinator to the static models and to the MIDAS Objects

Some of the fields of the miModule interface (see chapter 3) can be provided by directly <connect>ing the fields of the module coordinator with the miModule interface. Please refer to the description of the module coordinator at [201\\_ModuleCoordinator](#).

### 4.1 Authoring Support

The modules of the demo layout have been constructed mainly with the help of X3D-Edit, some parts (mainly the landscape) were generated with the help of Blender and Gimp.

It's planned to provide Blender Python Scripts together with the SRR Framework, so that modeling SrrTrains modules should become easier in the future.

## 5 Additional Info

### 5.1 The Fields of miModule

miModule is the external interface ("minimum interface") of an SrrTrains/SMUOS module. Module wrappers use modules via the miModule interface.

#### 5.1.1 commParam

After having loaded the module (and after the SSC has been initialized), the module wrapper sends a reference to the common parameters to this field and hence triggers the initialization / attachment of the module.

#### 5.1.2 moduleName

BEFORE triggering the initialization, the module wrapper sets the name of the module via this field. Please refer to [011\\_NamingRules](#) for further information.

#### 5.1.3 mwParam

BEFORE triggering the initialization, the module wrapper adds a reference to the module wrapper parameters. This is necessary, because the module coordinator needs access to the module wrapper.

#### 5.1.3 initialized

The module reports successful (initialized != NULL) or unsuccessful (initialized == NULL) initialization at this field.

#### 5.1.4 disable

The module wrapper disables and detaches the module, before he actually unloads the module, by setting the SFTIME field to a value "now".